

PL/PDF

PL/OFFX_DOCX

DOCX processor and generator

v4.9.4

PL/PDF

Contents

Introduction	1
Links	1
Installation	1
Using PL/OFFX_DOCX	1
Contact	1
Init	2
getScaleFactor	2
setPageSize	2
crParagraph	2
crSectionParagraph	3
addParagraph	3
addParagraph	3
addText	3
addText	4
addInstrText	5
addfldChar	5
crRun	5
addRun	5
addRun	6
addBR	6
addBR	6
setListLevel	6
AddHeader	7
AddFooter	7
crTable	7
addTable	7
addTable	8
setTableBorders	8
setTableTopBorder	8
setTableBottomBorder	8
setTableLeftBorder	9
setTableRightBorder	9
setTableInsideBorder	9
setTableInsideVBorder	10
AddRow	10
AddCell	10
TableaddParagraph	11
TableaddParagraph	11
addInlineImage	11
addInlineImage	11
SetBackground	12
addTabStop	12
addImage	12
addImage	13
AddSectionP	13
AddSectionB	14

PL/PDF

setSectPrPg	14
addSectionColumn	15
addPageNumField	15
addPageNumField	15
addDateField	15
addDateField	15
addAuthorField	16
addAuthorField	16
addHyperLink	16
addHyperLink	17
addTableOfContent	18
addTableOfContent	18
addField	18
getDoc	18
parseDoc	18
crList	18
AddListElement	19
crParagraphBorder	19
crBorder	19
crIndentation	20
crSpacing	20
crCellBorder	20
AddChart	21
getDocument	21
crUnderline	21
AddToHeader	21
AddToFooter	21

PL/PDF

Introduction

PL/OFFX_DOCX is a PL/SQL based DOCX document generator from Oracle databases. Use PL/OFFX_DOCX to quickly and easily develop applications with dynamic content but also quality presentation and printing capabilities.

Links

Overview of the XML file formats in Office 2010: <http://technet.microsoft.com/en-us/library/cc179190.aspx>

XML Wordprocessing document structure: [http://msdn.microsoft.com/en-us/library/office/qq278308\(v=office.15\).aspx](http://msdn.microsoft.com/en-us/library/office/qq278308(v=office.15).aspx)

Installation

System requirements: Oracle 11g RDBMS Release 2 or higher. Oracle 11g Express Edition is supported.

PL/OFFX_DOCX is a collection of PL/SQL packages. Before using PL/OFFX_DOCX, make sure that the steps described in the InstallationGuide were completed.

Using PL/OFFX_DOCX

Essentially, PL/OFFX_DOCX is a series of calls to PL/OFFX_DOCX procedures and functions from a PL/SQL script, package, procedure or function. If you are not familiar with the PL/SQL programming language, study the Oracle documentation.

Contact

Contact us at: <mailto:info@plpdf.com>

PL/PDF

Init

Type: procedure

Description: Initializes generator program variables.

Version: v2.0.0

Parameters:

- p_unit varchar2 default 'mm': Default measurement unit
- p_orientation ploffx_document_type.ST_PageOrientation default ploffx_document_type.c_portrait: Page orientation

Return: -

getScaleFactor

Type: function

Description: Gets the scale multiplier between user OUM and internal point.

Version: v4.8.0

Parameters:

-

Return: number: The multiplier

setPageSize

Type: procedure

Description: Set page size setting.

Version: v4.7.0

Parameters:

- p_w number: Page width
- p_h number: Page height

Return: -

crParagraph

Type: function

Description: Create empty paragraph for content.

Version: v2.0.0

Parameters:

- p_bidi boolean default null: Right to Left Paragraph Layout
- p_contextualSpacing boolean default null: Ignore Spacing Above and Below When Using Identical Styles
- p_ind ploffx_document_type.CT_Ind default null: Set paragraph indentation
- p_alignment varchar2 default null: Paragraph horizontal alignment (left, center, right, justify)
- p_pageBreakBefore boolean default null: Start Paragraph on Next Page
- p_border ploffx_document_type.CT_PBdr default null: Paragraph Borders
- p_pStyle varchar2 default null: Referenced Paragraph Style
- p_spacing number default null: Spacing Between Lines and Above/Below Paragraph
- p_suppressAutoHyphens boolean default null: Suppress Hyphenation for Paragraph
- p_suppressLineNumbers boolean default null: Suppress Line Numbers for

PL/PDF

Paragraph

- p_textAlignment varchar2 default null : Vertical Character Alignment on Line
- p_widowControl boolean default null : Allow First/Last Line to Display on a Separate Page
- p_widowControl boolean default null : p_numPr pls_integer default null

Return : pls_integer : Index of the created paragraph

crSectionParagraph

Type: function

Description : Create section paragraph for content.

Version: v4.8.0

Parameters :

- p_cols_space varchar2 default null : Column Definitions
- p_docgrid_linePitch varchar2 default null : Document Grid
- p_pgmar_bottom varchar2 default null : Page Margins Bottom
- p_pgmar_footer varchar2 default null : Page MArgins Footer
- p_pgmar_gutter varchar2 default null : Page Margins Gutter
- p_pgmar_header varchar2 default null : Page Margins Header
- p_pgmar_left varchar2 default null : Page Margins Left
- p_pgmar_right varchar2 default null : Page Margins Right
- p_pgmar_top varchar2 default null : Page Margins Top
- p_pgSz_w varchar2 default null : Page Size Width
- p_pgSz_h varchar2 default null : Page Size Height
- p_pgSz_orient varchar2 default null : Page Size Orientation

Return : pls_integer : Index of the created paragraph

addParagraph

Type: procedure

Description : Add paragraph to document

Version: v2.0.0

Parameters :

- p_paragraph_id pls_integer : Existing paragraph ID

Return : -

addParagraph

Type: function

Description : Add paragraph to document

Version: v2.0.0

Parameters :

- p_paragraph_id pls_integer : Existing paragraph ID

Return : pls_integer : The internal index of the new paragraph

addText

Type: procedure

Description : Add text to an existing paragraph.

Version: v2.0.0

Parameters :

PL/PDF

- p_paragraph_id pls_integer : Specifies a reference to a previously defined paragraph.
- p_text varchar2 : Specifies the value of this text.
- p_bold boolean default null : Bold text.
- p_border ploffx_document_type.CT_Border default null : Specifies text border properties
- p_case varchar2 default null : Specifies U(pper) or L(ower) case
- p_color varchar2 default null : Specifies text color in hexadecimal format
- p_fitText number default null : Display text in fix width.
- p_highlight varchar2 default null : Specifies highlight color around the text.
- p_italic boolean default null : Italic text.
- p_vertPosition number default null : Specifies the amount to be raised or lowered the text relation to the default baseline of the
- p_FontName varchar2 default nul : Specifies font family
- p_style varchar2 default null : Specifies the text style
- p_spacing number default null : Specifies the character spacing.
- p_strikeout number default null : Strikeout.
- p_FontSize number default null : Specifies the font size.
- p_underline ploffx_document_type.CT_Underline default null : Specifies the underline properties.
- p_vertAlign varchar2 default null : Specifies the vertical alignment of the text.
 - o baseline
 - o subscript
 - o superscript
- p_w number default null : This element specifies the amount by which each character shall be expanded.

Return : -

addText

Type: function

Description : Add text to an existing paragraph.

Version: v2.0.0

Parameters :

- p_paragraph_id pls_integer : Specifies a reference to a previously defined paragraph.
- p_text varchar2 : Specifies the value of this text.
- p_bold boolean default null : Bold text.
- p_border ploffx_document_type.CT_Border default null : Specifies text border properties
- p_case varchar2 default null : Specifies U(pper) or L(ower) case
- p_color varchar2 default null : Specifies text color in hexadecimal format
- p_fitText number default null : Display text in fix width.
- p_highlight varchar2 default null : Specifies highlight color around the text.
- p_italic boolean default null : Italic text.
- p_vertPosition number default null : Specifies the amount to be raised or lowered the text relation to the default baseline of the
- p_FontName varchar2 default nul : Specifies font family

PL/PDF

- p_style varchar2 default null : Specifies the text style
- p_spacing number default null : Specifies the character spacing.
- p_strikeout number default null : Strikeout.
- p_FontSize number default null : Specifies the font size.
- p_underline plofff_document_type.CT_Underline default null : Specifies the underline properties.
- p_vertAlign varchar2 default null : Specifies the vertical alignment of the text.
 - o baseline
 - o subscript
 - o superscript
- p_w number default null : This element specifies the amount by which each character shall be expanded.

Return : pls_integer : The internal index of the text object

addInstrText

Type: function

Description : Adds Field Code to an existing paragraph.

Version: v4.9.4

Parameters :

- p_paragraph_id pls_integer : Specifies a reference to a previously defined paragraph.
- p_instrText varchar2 : Specifies the value of this field code.
- p_RPr plofff_document_type.CT_RPr default null : the field code run properties

Return : pls_integer : The internal index of the text object

addfldChar

Type: function

Description : Adds Complex Field Char to an existing paragraph.

Version: v4.8.2

Parameters :

- p_paragraph_id pls_integer : Specifies a reference to a previously defined paragraph.
- p_fldCharType varchar2 : Specifies the value of this field char.

Return : pls_integer : The internal index of the text object

crRun

Type: function

Description : Creates text run structure from text and run properties.

Version: v4.8.0

Parameters :

- p_text varchar2 : The text as string
- p_RPr plofff_document_type.CT_RPr : The run properties

Return : pls_integer : The internal structure of the created object

addRun

PL/PDF

Type: function

Description: Adds Run as a structure to an existing paragraph.

Version: v4.8.0

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_run ploffx_document_type.CT_R: The run as internal structure

Return: pls_integer: The internal index of the run object

addRun

Type: procedure

Description: Adds Run as a structure to an existing paragraph.

Version: v4.8.0

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_run ploffx_document_type.CT_R: The run as internal structure

Return: -

addBR

Type: function

Description: Adds Break to an existing paragraph.

Version: v4.5.0

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_clear varchar2 default null: Restart Location For Text Wrapping Break
- p_type varchar2 default null: Break Type, see ploffx_document_type.ST_BrType
 - o column: Column Break
 - o page: Page Break
 - o textWrapping: Line Break

Return: pls_integer: The internal index of the run object

addBR

Type: procedure

Description: Adds Break to an existing paragraph.

Version: v4.8.0

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_clear varchar2 default null: Restart Location For Text Wrapping Break
- p_type varchar2 default null: Break Type, see ploffx_document_type.ST_BrType
 - o column: Column Break
 - o page: Page Break
 - o textWrapping: Line Break

Return: -

setListLevel

Type: procedure

Description: Set paragraph to a list element.

Version: v2.0.0

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_level pls_integer default 0: Specifies the list level.
- p_numId pls_integer default 1: Specifies a reference to the list.

Return: -

AddHeader

Type: procedure

Description: Add paragraph to the document header.

Version: v3.0.0

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_type ploffx_document_type.ST_HdrFtr default ploffx_document_type.c_default: Specifies the type of header.
 - o default
 - o even
 - o first

Return:

AddFooter

Type: procedure

Description: Add paragraph to the document footer.

Version: v3.0.0

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_type ploffx_document_type.ST_HdrFtr default ploffx_document_type.c_default: Specifies the type of footer.
 - o default
 - o even
 - o first

Return:

crTable

Type: function

Description: Create table.

Version: v4.8.1

Parameters:

- p_width number default null: Specifies the table width.
- p_alignment varchar2 default ploffx_document_type.c_left: Specifies the table alignment.
- p_tblStyle varchar2 default null: Specifies the table style.

Return: pls_integer: Index of the created table

addTable

Type: function

Description: Add previously defined table to the document.

Version: v2.0.0

Parameters:

- p_table_id pls_integer: Specifies a reference to a previously defined table.

Return: pls_integer: Index of the created table.

addTable

Type: procedure

Description: Add previously defined table to the document.

Version: v4.8.0

Parameters:

- p_table_id pls_integer: Specifies a reference to a previously defined table.

Return: -

setTableBorders

Type: procedure

Description: Customize a previously defined table border properties.

Version: v2.0.0

Parameters:

- p_table_id pls_integer: Specifies a reference to a previously defined table.
- p_style varchar2 default null: Specifies the border style.
- p_width number default null: Specifies the border width.
- p_space number default null: Specifies the space between the border and the content.
- p_color varchar2 default null: Specifies the border color.

Return: -

setTableTopBorder

Type: procedure

Description: Customize a previously defined table top border properties.

Version: v4.7.0

Parameters:

- p_table_id pls_integer: Specifies a reference to a previously defined table.
- p_style varchar2 default null: Specifies the border style.
- p_width number default null: Specifies the border width.
- p_space number default null: Specifies the space between the border and the content.
- p_color varchar2 default null: Specifies the border color.

Return: -

setTableBottomBorder

Type: procedure

Description: Customize a previously defined table bottom border properties.

Version: v4.7.0

Parameters:

- p_table_id pls_integer: Specifies a reference to a previously defined table.
- p_style varchar2 default null: Specifies the border style.
- p_width number default null: Specifies the border width.
- p_space number default null: Specifies the space between the border and the content.
- p_color varchar2 default null: Specifies the border color.

Return: -

setTableLeftBorder

Type: procedure

Description: Customize a previously defined table left border properties.

Version: v4.7.0

Parameters:

- p_table_id pls_integer: Specifies a reference to a previously defined table.
- p_style varchar2 default null: Specifies the border style.
- p_width number default null: Specifies the border width.
- p_space number default null: Specifies the space between the border and the content.
- p_color varchar2 default null: Specifies the border color.

Return: -

setTableRightBorder

Type: procedure

Description: Customize a previously defined table right border properties.

Version: v4.7.0

Parameters:

- p_table_id pls_integer: Specifies a reference to a previously defined table.
- p_style varchar2 default null: Specifies the border style.
- p_width number default null: Specifies the border width.
- p_space number default null: Specifies the space between the border and the content.
- p_color varchar2 default null: Specifies the border color.

Return: -

setTableInsideBorder

Type: procedure

Description: Customize a previously defined table InsideH border properties.

Version: v4.7.0

Parameters:

- p_table_id pls_integer: Specifies a reference to a previously defined table.

PL/PDF

- p_style varchar2 default null : Specifies the border style.
- p_width number default null : Specifies the border width.
- p_space number default null : Specifies the space between the border and the content.
- p_color varchar2 default null : Specifies the border color.

Return : -

setTableInsideVBorder

Type: procedure

Description : Customize a previously defined table InsideV border properties.

Version: v4.7.0

Parameters :

- p_table_id pls_integer : Specifies a reference to a previously defined table.
- p_style varchar2 default null : Specifies the border style.
- p_width number default null : Specifies the border width.
- p_space number default null : Specifies the space between the border and the content.
- p_color varchar2 default null : Specifies the border color.

Return : -

AddRow

Type: function

Description : Add row to a previously defined table.

Version: v4.5.0

Parameters :

- p_table_id pls_integer : Specifies a reference to a previously defined table.
- p_alignment varchar2 default null : Specifies the alignment of the row.
- p_height number default null : Specifies the height of the row.
- p_ttblheader boolean default null : Repeat table row on every new page.

Return : pls_integer : Index of the created row.

AddCell

Type: function

Description : Add cell to a previously defined table row.

Version: v4.9.3

Parameters :

- p_table_id pls_integer : Specifies a reference to a previously defined table.
- p_row_id pls_integer : Specifies a reference to a previously defined row.
- p_noWrap boolean default null : NoWrap.
- p_width number default null : Specifies the width of the cell.
- p_gridSpan pls_integer default null : This element specifies the number of grid columns which shall be spanned by the current cell.
- p_cellBorder plofff_document_type.CT_TcBorders default null : Specifies the border of the cell.
- p_background plofff_document_type.ST_HexColor default null : Specifies the

PL/PDF

background color of the cell.

Return: pls_integer: Index of the created cell.

TableaddParagraph

Type: procedure

Description: Add previously defined paragraph to a cell of table.

Version: v2.0.0

Parameters:

- p_table_id pls_integer: Specifies a reference to a previously defined table.
- p_row_id pls_integer: Specifies a reference to a previously defined row.
- p_cell_id pls_integer: Specifies a reference to a previously defined cell.
- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.

TableaddParagraph

Type: function

Description: Add previously defined paragraph to a cell of table.

Version: v2.0.0

Parameters:

- p_table_id pls_integer: Specifies a reference to a previously defined table.
- p_row_id pls_integer: Specifies a reference to a previously defined row.
- p_cell_id pls_integer: Specifies a reference to a previously defined cell.
- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.

Return: pls_integer: The internal index of the paragraph

addInlineImage

Type: procedure

Description: Add inline image to a paragraph.

Version: v4.9.1

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_name varchar2: Specifies the image name.
- p_file in out nocopy blob: Specifies a reference to the image source blob.
- p_width number default null: Specifies the image width.
- p_height number default null: Specifies the image height.

addInlineImage

Type: function

Description: Add inline image to a paragraph.

Version: v4.9.1

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.

PL/PDF

- p_name varchar2: Specifies the image name.
- p_file in out nocopy blob: Specifies a reference to the image source blob.
- p_width number default null: Specifies the image width.
- p_height number default null: Specifies the image height.

Return: pls_integer: tThe internal index of the image

SetBackground

Type: procedure

Description: Change the background color of document.

Version: v2.0.0

Parameters:

- p_backcolor varchar2: Specifies the background color of document, in hexadecimal RGB code.

Return: -

addTabStop

Type: procedure

Description: Add tab stop to a selected paragraph

Version: v2.0.0

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_val ploffx_document_type.ST_TabJc: Specifies the type of tab stop.
- p_pos number: Specifies the position of tab stop.
- p_leader ploffx_document_type.ST_TabTlc default ploffx_document_type.c_none_Tlc: Specifies the character which shall be used to fill in the space created by a tab which ends at this custom tab stop

Return: -

addImage

Type: function

Description: Add inline image to a paragraph.

Version: v4.9.1

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_name varchar2: Specifies the image name.
- p_file in out nocopy blob: Specifies a reference to the image source blob.
- p_width number default null: Specifies the image width.
- p_height number default null: Specifies the image height.
- p_x number: Specifies the image x coordinate of position.
- p_y number: Specifies the image y coordinate of position.
- p_textWrap varchar2 default 'wrapSquare': Specifies the text wrap around the image.
- p_relativeFromH varchar2 default 'column': This element specifies the horizontal positioning of the image.
- p_relativeFromV varchar2 default 'paragraph': This element specifies the vertical positioning of the image.

PL/PDF

- p_locked boolean default false : Lock the image location when an application edits the document.
- p_layoutInCell boolean default true : Specifies how image shall behave when its anchor is located in a table cell.
- p_allowOverlap boolean default true : Specifies how image shall behave when its anchor is located in a table cell display time shall be allowed to overlap the contents of the other image.
- p_behindDoc varchar2 default 'false' : Specifes the image to be displayed behind or above of the content.

Return : pls_integer : Index of the added image.

addImage

Type: procedure

Description : Add inline image to a paragraph.

Version: v4.9.4

Parameters :

- p_paragraph_id pls_integer : Specifies a reference to a previously defined paragraph.
- p_name varchar2 : Specifies the image name.
- p_file in out nocopy blob : Specifies a reference to the image source blob.
- p_width number default null : Specifies the image width.
- p_height number default null : Specifies the image height.
- p_x number : Specifies the image x coordinate of position.
- ?p_y number : Specifies the image y coordinate of position.
- p_textWrap varchar2 default 'wrapSquare' : Specifies the text wrap around the image.
- p_relativeFromH varchar2 default 'column' : This element specifies the horizontal positioning of the image.
- p_relativeFromV varchar2 default 'paragraph' : This element specifies the vertical positioning of the image.
- p_locked boolean default false : Lock the image location when an application edits the document.
- p_layoutInCell boolean default true : Specifies how image shall behave when its anchor is located in a table cell.
- p_allowOverlap boolean default true : Specifies how image shall behave when its anchor is located in a table cell display time shall be allowed to overlap the contents of the other image.
- p_behindDoc varchar2 default 'false' : Specifes the image to be displayed behind or above of the content.

Return : -

AddSectionP

Type: function

Description : Add section for paragraph.

Version: v2.0.0

Parameters :

- p_paragraph_id pls_integer : Specifies a reference to a previously defined paragraph.
- p_num number default null : Specifies the number of columns.

PL/PDF

- p_space number default null: Specifies the space between the columns.
- p_type plofff_document_type.ST_SectionMark: Specifies the type of the break point.

Return: pls_integer: Index of the added section.

AddSectionB

Type: function

Description: Add section for body.

Version: v2.0.0

Parameters:

- p_paragraph_id pls_integer default null: Specifies a reference to a previously defined paragraph. If null, then will be create a new paragraph.
- p_num number default null: Specifies the number of columns.
- p_space number default null: Specifies the space between the columns.
- p_type plofff_document_type.ST_SectionMark: Specifies the type of the break point.

Return: pls_integer: Index of the added section.

setSectPrPg

Type: procedure

Description: Set section properties.

Version: v2.0.0

Parameters:

- p_section_id pls_integer default 0: Specifies a reference to a previously defined section.
- p_w plx_sc.normalv2 default null: Specifies the page width.
- p_h plx_sc.normalv2 default null: Specifies the page height.
- p_orient plofff_util.t_string default null: Specifies the page orientation.
- p_code plx_sc.normalv2 default null: Specifies a printer-specific paper code.
- p_bottom plx_sc.normalv2 default null: Specifies the distance between the bottom of the text margins for the main document and the bottom of the page for all pages in this section.
- p_footer plx_sc.normalv2 default null: Specifies the distance from the bottom edge of the page to the bottom edge of the footer.
- p_gutter plx_sc.normalv2 default null: Specifies the page gutter for each page in the current section.
- p_header plx_sc.normalv2 default null: Specifies the distance from the top edge of the page to the top edge of the header.
- p_left plx_sc.normalv2 default null: Specifies the distance between the left edge of the page and the left edge of the text extents for this document.
- p_right plx_sc.normalv2 default null: Specifies the distance between the right edge of the page and the right edge of the text extents for this document.
- p_top plx_sc.normalv2 default null: Specifies the distance between the top of the text margins for the main document and the top of the page for all pages in this section.

Return : -

addSectionColumn

Type: procedure

Description: Add section column to a previously created section.

Version: v2.0.0

Parameters :

- p_section_id pls_integer default 0 : Specifies a reference to a previously defined section.
- p_num number : Number of columns.
- p_space number : Space between columns.

Return : -

addPageNumField

Type: function

Description: Add page number to a header or footer paragraph.

Version: v2.0.0

Parameters :

- p_paragraph_id pls_integer : Specifies a reference to a previously defined paragraph. If null, then will be create a new paragraph.
- p_format varchar2 default ' * Arabic ' : Specifies the format of the page number. In default case it use the arabic numbers.

Return : pls_integer : Index of the added page number.

addPageNumField

Type: procedure

Description: Add page number to a header or footer paragraph.

Version: v4.9.4

Parameters :

- p_paragraph_id pls_integer : Specifies a reference to a previously defined paragraph. If null, then will be create a new paragraph.
- p_format varchar2 default ' * Arabic ' : Specifies the format of the page number. In default case it use the arabic numbers.

Return : -

addDateField

Type: function

Description: Add date field to a paragraph.

Version: v2.0.0

Parameters :

- p_paragraph_id pls_integer : Specifies a reference to a previously defined paragraph.
- p_format varchar2 default ' \@ yyyy-MM-dd ' : Specifies the date format.

Return : pls_integer : Index of the added date field.

addDateField

PL/PDF

Type: procedure

Description: Add date field to a paragraph.

Version: v4.9.4

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_format varchar2 default '@ yyyy-MM-dd': Specifies the date format.

Return: -

addAuthorField

Type: function

Description: Add author field to a previously defined paragraph.

Version: v2.0.0

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_format varchar2 default null: Specifies the date format.

Return: pls_integer: Index of the added author field.

addAuthorField

Type: procedure

Description: Add author field to a previously defined paragraph.

Version: v4.9.4

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_format varchar2 default null: Specifies the date format.

Return: -

addHyperLink

Type: procedure

Description: Add hyperlink to a previously defined paragraph.

Version: v2.0.0

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_text varchar2: The hyperlink text.
- p_url varchar2: The hyperlink URL
- p_bold boolean default null: Bold text.
- p_border plofff_document_type.CT_Border default null: Specifies hyperlink border.
- p_case varchar2 default null: U(pper)/L(ower)case.
- p_color varchar2 default null: Specifies hyperlink text color.
- p_fitText number default null: Display text in fix width.
- p_highlight varchar2 default null: Specifies highlight color around the text.
- p_italic boolean default null: Italic text.
- p_vertPosition number default null: Specifies the amount to be raised or

PL/PDF

lowered the text relation to the default baseline of the

- p_FontName varchar2 default nul : Specifies font family
- p_style varchar2 default null : Specifies the text style
- p_spacing number default null : Specifies the character spacing.
- p_strikeout number default null : Strikeout.
- p_FontSize number default null : Specifies the font size.
- p_underline ploffx_document_type.CT_Underline default null : Specifies the underline properties.
- p_vertAlign varchar2 default null : Specifies the vertical alignment of the text.
 - o baseline
 - o subscript
 - o superscript
- p_w number default null : This element specifies the amount by which each character shall be expanded.

Return : pls_integer : The internal index of the hyperlink object.

addHyperLink

Type: function

Description : Add hyperlink to a previously defined paragraph.

Version: v2.0.0

Parameters :

- p_paragraph_id pls_integer : Specifies a reference to a previously defined paragraph.
- p_text varchar2 : The hyperlink text.
- p_url varchar2 : The hyperlink URL
- p_bold boolean default null : Bold text.
- p_border ploffx_document_type.CT_Border default null : Specifies hyperlink border.
- p_case varchar2 default null : U(pper)/L(ower)case.
- p_color varchar2 default null : Specifies hyperlink text color.
- p_fitText number default null : Display text in fix width.
- p_highlight varchar2 default null : Specifies highlight color around the text.
- p_italic boolean default null : Italic text.
- p_vertPosition number default null : Specifies the amount to be raised or lowered the text relation to the default baseline of the
- p_FontName varchar2 default nul : Specifies font family
- p_style varchar2 default null : Specifies the text style
- p_spacing number default null : Specifies the character spacing.
- p_strikeout number default null : Strikeout.
- p_FontSize number default null : Specifies the font size.
- p_underline ploffx_document_type.CT_Underline default null : Specifies the underline properties.
- p_vertAlign varchar2 default null : Specifies the vertical alignment of the text.
 - o baseline
 - o subscript
 - o superscript
- p_w number default null : This element specifies the amount by which each

PL/PDF

character shall be expanded.

addTableOfContent

Type: function

Description: Add table of content to a previously defined paragraph.

Version: v2.0.0

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.

Return: pls_integer: Index of the added table of content.

addTableOfContent

Type: procedure

Description: Add table of content to a previously defined paragraph.

Version: v4.9.4

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.

Return: -

addField

Type: function

Description: Add field to a perviously defined paragraph.

Version: v2.0.0

Parameters:

- p_paragraph_id pls_integer: Specifies a reference to a previously defined paragraph.
- p_code varchar2: Specifies the field codes for the simple field.

Return: pls_integer: Index of the added field.

getDoc

Type: procedure

Description: Returns the generated document. The document is closed and then returned.

Version: v2.0.0

Parameters: -

Return: -

parseDoc

Type: Processing docx files.

Description:

Version: v2.0.0

Parameters: -

Return: -

crList

Type: function

Description: Returns the ID of the created list.

Version: v3.0.0

Parameters:

- p_startValue pls_integer default 1: Specifies the starting number for the listing.
- p_symbol XT_NUMBERING default numbering_symbol: Specifies the style of the list.

Return: pls_integer

AddListElement

Type: procedure

Description: Adds an element to a list

Version: v3.0.0

Parameters:

- p_paragraph_id pls_integer: Specifies the paragraph of the element that will be added to the list
- p_level pls_integer default 0: Specifies the level of the element(0-8)
- p_list pls_integer default 1: Specifies the list for the element to be added to.

Return: -

crParagraphBorder

Type: function

Description: Creates a paragraph border

Version: v3.0.0

Parameters:

- p_top ploffx_document_type.CT_Border default null: Specifies the top border of the paragraph
- p_bottom ploffx_document_type.CT_Border default null: Specifies the bottom border of the paragraph
- p_left ploffx_document_type.CT_Border default null: Specifies the left border of the paragraph
- p_right ploffx_document_type.CT_Border default null: Specifies the right border of the paragraph

Return: ploffx_document_type.CT_PBdr: Returns a paragraph border which can be passed to crParagraph function

crBorder

Type: function

Description: Creates a paragraph border

Version: v3.0.0

Parameters:

- p_style ploffx_document_type.ST_Border default null: Specifies the style of the border
- p_color ploffx_document_type.ST_HexColor default null: Specifies the color of the border
- p_width number default null: Specifies the width of the border in points

PL/PDF

- p_spacing number default null : Specifies the spacing between the border and the area
- p_shadow boolean default null : Specifies the border has shadow
- p_frame boolean default null : Specifies the border has frame

Return : ploffx_document_type.CT_Border : Returns a border which can be passed to crParagraphBorder function or AddText procedure

crIndentation

Type: function

Description : Creates an indentation

Version: v3.0.0

Parameters :

- p_left number default null : Specifies the left indentation of the paragraph in units
- p_right number default null : Specifies the right indentation of the paragraph in units
- p_hanging number default null : Specifies the hanging indentation in units
- p_firstLine number default null : Specifies the indentation of the first of the paragraph in units

Return : ploffx_document_type.CT_PBdr : Returns an indentation which can be passed to crParagraph function

crSpacing

Type: function

Description : Creates a paragraph spacing

Version: v3.0.0

Parameters :

- p_before number default null : Specifies the spacing before the paragraph in points
- p_after number default null : Specifies the spacing after the paragraph in points
- p_linespace number default null : Specifies the line spacing of the paragraph in lines

Return : ploffx_document_type.CT_Spacing : Returns a paragraph spacing which can be passed to crParagraph function

crCellBorder

Type: function

Description : Creates a table cell border

Version: v3.5.0

Parameters :

- p_top ploffx_document_type.CT_Border default null : Specifies the top side border
- p_bottom ploffx_document_type.CT_Border default null : Specifies the bottom side border
- p_left ploffx_document_type.CT_Border default null : Specifies the left side border
- p_right ploffx_document_type.CT_Border default null : Specifies the right

side border

Return: ploffx_document_type.CT_TcBorders: Returns a border which can be passed to crCell function

AddChart

Type: function

Description: Add chart to a previous created paragraph.

Version: v3.6.0

Parameters:

- p_paragraph_id pls_integer: Specifies an existing paragraph
- p_chart ploffx_chart.CT_ChartSpace: Specifies an existing Chart
- p_x number default null: Specifies horizontal starting point
- p_y number default null: Specifies vertical starting point
- p_width number default null: Specifies the Chart area width
- p_height number default null: Specifies the Chart area width

Return: -

getDocument

Type: function

Description: Get the full docx document structure.

Version: v3.6.0

Parameters: -

Return: -

crUnderline

Type: function

Description: Create underline line type.

Version: v3.6.0

Parameters:

- p_type ploffx_document_type.ST_Underline: Create underline type.

Return: ploffx_document_type.CT_Underline: Return a line type which using to underline.

AddToHeader

Type: procedure

Description: Add an existing element to the document header.

Version: v3.0.0

Parameters:

- p_header ploffx_document_type.ST_HdrFtr default ploffx_document_type.c_default_hfr: Specifies the header type
- p_element_id pls_integer: Specifies the element id.

Return: -

AddToFooter

Type: procedure

Description: Add an existing element to the document footer.

PL/PDF

Version: v3.0.0

Parameters :

- p_footer ploffx_document_type.ST_HdrFtr default
- ploffx_document_type.c_default_hfr : Specifies the header type
- p_element_id pls_integer : Specifies the element id.

Return : -