

PL/PDF

PL/PDF

User's Guide

v5.0

PL/PDF

Contents

Introduction	1
Installation	1
Using PL/PDF	1
Documentation	1
Code Examples	1
Contact	1
Certification	2
GetCertKey	2
checkCertKey	2
getLicencedProductsV4	2
Administrative commands	3
AddCJKFont	3
AddTTF	3
init	3
init1	3
getVersion	4
setRotatePages	4
sendDoc	4
setAllMargin	4
setAutoNewPage	5
setNOCompress	5
setDocAuthor	5
setDocCreator	5
setDocDisplayMode	5
setDocKeywords	6
setDocSubject	6
SetDocTitle	6
setEncoding	6
setHeaderProcName	7
setHeaderProcName5	7
set3HeaderProcName	8
setFooterProcName	8
setFooterProcName5	8
set3FooterProcName	9
setBackgroundColor	9
SetWatermarkProcName	9
SetStampProcName	9
setNewPageProcName	9
setLeftMargin	10
setTopMargin	10
setRightMargin	10
setBottomMargin	10
setNOLastpageProcName	10
SetPageNoStart	11
SetPageNoEnd	11
getPageNoAlter	11

PL/PDF

SetProtection	11
setPDFAlB	11
setID	11
Navigations and formatting commands	13
checkPageBreak	13
getCurrPageNum	13
getNumOfPages	13
getLeftMargin	13
getRightMargin	13
getTopMargin	13
getBottomMargin	14
getHeaderHeight	14
getFooterHeight	14
getCurrentX	14
getCurrentY	14
getPageAvailableHeight	14
getPageAvailableWidth	15
getPageHeight	15
getPageRightSpace	15
getPageLeftSpace	15
getPageSpace	15
getPageWidth	15
getPageBottomSpace	16
getPrintFontKey	16
getPrintFontName	16
getPrintFontStyle	16
getPrintFontSize	16
getScaleFactor	16
getTextWidth	16
getTextwidthFont	17
removeMissingChars	17
insertMovePage	17
NewPage	17
SetNoPrintFooter	18
setNoPrintHeader	18
setCurrentX	18
setCurrentY	18
setCurrentXY	18
NewLine	19
Content Related Commands	20
AttachFile	20
crBookmark	20
PrintoutText	20
Circle	20
Ellipse	21
Line	21
Polygon	21
Path	22
Rect	22
RoundedRect	22
Sector	23

PL/PDF

EndOpacity	23
EndOptCont	23
putImage	23
putImage	24
putImage	24
putInternalLink	24
putExternalLink	25
putLink	25
setStrokingColor	25
setNonStrokingColor	25
addJavaScript	26
LineWidth	26
crInternalLink	26
setLinkDest	26
crInternalLinkDest	26
setPrintFont	27
setPrintFontSize	27
setRotate	27
startClipping	28
EndClipping	28
isInClipping	28
startOpacity	28
startOptCont	28
Template Related Commands	30
InsTemplate	30
setPageTemplate	30
setPageDefaultTemplate	30
UseTemplate	30
Digital Signature Related Commands	31
setDigSig	31
setNeedAppearances	31
getCalcCurrPageNum	31
getCalcCurrPageNum	31
PL/PDF v2 Compatible procedures and functions	33
LineBreak	33
setLineWidth	33
getLineWidth	33
DrawLine	33
DrawRect	33
drawRoundedRect	34
DrawEllipse	34
DrawCircle	34
drawSector	35
DrawPolygon	35
PrintText	35
setCellMargin	35
getCellMargin	36
setCellBottomMargin	36
setCellLeftMargin	36
setCellRightMargin	36
setCellTopMargin	36

PL/PDF

getCellBottomMargin	36
getCellLeftMargin	37
getCellRightMargin	37
getCellTopMargin	37
getTextHeight	37
getCellMinHeight	37
getCellMinHeightFont	37
getCellMinWidth	38
getCellMinWidthFont	38
PrintCell	39
PrintMultiLineCell	39
PrintFlowingText	40
PrintFlowingTextLimit	41
PrintImageCell	41
setColor4Drawing	42
setColor4Drawing	42
setColor4Filling	43
setColor4Filling	43
setColor4Text	43
setColor4Text	43
getColor4Drawing	43
getColor4Filling	44
getColor4Text	44

PL/PDF

Introduction

PL/PDF is a PL/SQL based PDF document generator from Oracle databases. Use PL/PDF to quickly and easily develop applications with dynamic content but also quality presentation and printing capabilities.

Installation

Before using PL/PDF, make sure that the steps described in the Installation Guide were completed.

Using PL/PDF

Essentially, PL/PDF is a series of calls to PL/PDF procedures and functions from a PL/SQL script, package, procedure or function. If you are not familiar with the PL/SQL programming language, study the Oracle documentation.

Documentation

The PL/PDF documentation is available at: <http://www.plpdf.com/downloads>

Code Examples

PL/PDF code examples can be found at: <http://plpdf.com/index.php/support/examples/>

Contact

Contact us at: <mailto:info@plpdf.com>

Certification

GetCertKey

Type: Function

Description: Generates preliminary certification key. This function should be run once when the PL/PDF package is installed. The function generates a string that should be sent to <mailto:info@plpdf.com>. Our representatives will send a certificate key back that should be used as the return value in the `pl_pdf_cert.SetCertKey` function.

Version: v3.0.0

Parameters: -

Return: varchar2: Preliminary certificate key

checkCertKey

Type: Function

Description: Checks the certification key.

Usage:

declare

l_ret boolean;

begin

l_ret := plpdf.checkCertKey;

if l_ret then

dbms_output.put_line('true');

else

dbms_output.put_line('false');

end if;

end;

Version: v3.0.0

Parameters: -

Return: boolean: validity of the key

getLicencedProductsV4

Type: Function

Description: This function returns with licence informations as a string.

Version: v4.1.0

Parameters: -

Return: varchar2: Licence

Administrative commands

AddCJKFont

Type: Procedure

Description: Add CJK (Chinese/Japanese/Korean) font.

Version: v3.0.0

Parameters:

- p_name varchar2: name of font
 - o japanese: 'HeiseiKakuGo-W5'
 - o korean: 'HYSMyeongJoStd-Medium-Acro'
 - o chinese: 'MSungStd-Light-Acro', 'STSongStd-Light-Acro'

Return: -

AddTTF

Type: Procedure

Description: Imports a TTF (True Type Font). The imported font becomes available to the SetPrintFont procedure. The font is stored as binary data in the PDF file.

Version: v3.0.0

Parameters:

- p_family varchar2: TTF name
- p_style varchar2 default null: Font style
 - o null: Regular
 - o B: Bold
 - o I: Italic
 - o BI or IB: Bold and Italic
- p_data t_addfont: Data structure necessary to insert the font. It contains the font definition binary file as well
- p_embed boolean default true: PDF contains TTF binary file or not

Return: -

init

Type: Procedure

Description: Initializes generator program variables.

Version: v3.0.0

Parameters:

- p_orientation varchar2 default 'P': Orientation
 - o P: portrait
 - o L: landscape
- p_unit varchar2 default 'mm': Unit of measure
- p_format varchar2 default 'A4': Page format

Return: -

init1

Type: Procedure

PL/PDF

Description: Initializes generator program variables.

Version: v3.0.0

Parameters:

- p_orientation varchar2 default 'P': Orientation
 - o P: portrait
 - o L: landscape
- p_unit varchar2 default 'mm': Unit of measure
- p_format plpdf_type.t_pageformat: see plpdf_const package for predefined pageformats

Return: -

getVersion

Type: Function

Description: Gets the version number of pl/plpdf package.

Version: v3.0.0

Parameters: -

Return: varchar2: number of current version

setRotatePages

Type: Procedure

Description: Sets the degree of rotation for all pages. The value must be a multiple of 90.

Version: v3.0.0

Parameters:

- p_angle number default 0: Angle/degree of rotation

Return: -

sendDoc

Type: Procedure

Description: Returns the generated PDF document. The document is closed and then returned in the OUT parameter.

Version: v4.8.3

Parameters:

- p_blob out nocopy blob: the generated document
- p_freemp boolean default true: frees the temporary BLOB variable of the PDF file in your default temporary tablespace

Return: -

setAllMargin

Type: Procedure

Description: Sets the margin size.

Version: v3.0.0

Parameters:

- p_left number: Left margin size
- p_top number: Top margin size
- p_right number default null: Right margin size. If null then the right margin will be the same as the left margin

PL/PDF

Return : -

setAutoNewPage

Type: Procedure

Description: Enables or disables automatic page breaks. The p_margin parameter is only relevant when enabling automatic page breaks. It sets the bottommargin size under which an automatic page break is triggered.

Version: v3.0.0

Parameters :

- p_auto boolean default true : Automatic page break
 - o true: Enable
 - o false: Disable
- p_margin number default 0 : Bottom margin size, if not set, then 1 cm

Return : -

setNOCompress

Type: Procedure

Description: Disables the compression of PDF documents. By default compression is enabled.

Version: v3.0.0

Return : -

setDocAuthor

Type: Procedure

Description: Sets the document author.

Version: v3.0.0

Parameters :

- p_author varchar2 : Document author

Return : -

setDocCreator

Type: Procedure

Description: Sets the document creator.

Version: v3.0.0

Parameters :

- p_creator varchar2 : Document creator

Return : -

setDocDisplayMode

Type: Procedure

Description: Sets how to display the document in a PDF viewer (e.g. Acrobat Reader).

Version: v3.0.0

Parameters :

- p_zoom varchar2 : Layout view
 - o fullpage: fits as full page

PL/PDF

- o fullwidth: fits as full width
- o real: fits in actual size
- o default: displays according to the setting of the PDF viewer
- p_layout varchar2 default 'continuous' : Page layout
 - o single: displays single pages
 - o continuous: displays pages continuously
 - o default: displays according to the setting of the PDF viewer
- p_hidemenubar boolean default false : A flag specifying whether to hide the viewer application's menu bar when the document is active.
- p_hidetoolbar boolean default false : A flag specifying whether to hide the viewer application's tool bars when the document is active.
- p_hidewindowui boolean default false : A flag specifying whether to hide user interface elements in the document's window (such as scrollbars and navigation controls), leaving only the document's contents displayed.
- p_displaydoctitle boolean default false : A flag specifying whether the window's title bar should display the document title taken from theTitle entry of the document information dictionary.
- p_centerwindow boolean default false : A flag specifying whether to position the document's window in the center of the screen.
- p_fitwindow boolean default false : A flag specifying whether to resize the document's window to fit the size of the first displayed page.

Return : -

setDocKeywords

Type: Procedure

Description : Sets the document keywords.

Version: v3.0.0

Parameters :

- p_keywords varchar2 : Keyword list

Return : -

setDocSubject

Type: Procedure

Description : Sets the document subject.

Version: v3.0.0

Parameters :

- p_subject varchar2 : Document subject

Return : -

SetDocTitle

Type: Procedure

Description : Sets the document title.

Version: v3.0.0

Parameters :

- p_title varchar2 : Document title

Return : -

setEncoding

PL/PDF

Type: Procedure

Description: Sets Adobe Core character encoding (default code is cp1252).

Version: v3.0.0

Parameters:

- p_enc varchar2: Character encoding code
 - o cp1250
 - o cp1251
 - o cp1252: this is the default, no need to set
 - o cp1253
 - o cp1254
 - o cp1255
 - o cp1256
 - o cp1257
 - o cp1258
 - o cp874
 - o iso-8859-1
 - o iso-8859-2
 - o iso-8859-4
 - o iso-8859-5
 - o iso-8859-7
 - o iso-8859-9
 - o iso-8859-15
 - o iso-8859-16
- o utf16: AL32UTF8 database with unicode TTF embending

Return: -

setHeaderProcName

Type: Procedure

Description: Sets the page header procedure name. The program name passed as a parameter executes when the page header is created. If setHeaderProcName is not executed before a page header is created then the page header will be empty.

Version: v3.0.0

Parameters:

- p_proc_name varchar2: Page header procedure name
- p_height number: height of header section

Return: -

setHeaderProcName5

Type: Procedure

Description: Sets the page header procedure name with 5 parameters. The program name passed as a parameter executes when the page header is created. If setHeaderProcName is not executed before a page header is created then the page header will be empty.

Version: v3.0.0

Parameters:

- p_proc_name varchar2: Page header procedure name
- p_height number: height of header section
- p_1 varchar2 default null: parameter of header procedure

PL/PDF

- p_2 varchar2 default null : parameter of header procedure
- p_3 varchar2 default null : parameter of header procedure
- p_4 varchar2 default null : parameter of header procedure
- p_5 varchar2 default null : parameter of header procedure

Return : -

set3HeaderProcName

Type: Procedure

Description: Sets the page header procedure names. The program name passed as a parameter executes when the page header is created.

Version: v3.0.1

Parameters :

- p_default_proc_name varchar2 default null : Specifies that this header shall appear on every page in this section which is not overridden with a specific even or first page header.
- p_first_proc_name varchar2 default null : Specifies that this header shall appear on the first page in this document.
- p_even_proc_name varchar2 default null : Specifies that this header shall appear on all even numbered pages in this document.
- p_height number : height of header section

Return : -

setFooterProcName

Type: Procedure

Description: Sets the page footer procedure name. The program name passed as a parameter executes when the page footer is created. If SetFooterProcName is not executed before a page footer is created then the page footer will be empty.

Version: v3.0.0

Parameters :

- p_proc_name varchar2 : Page header procedure name
- p_height number : height of header section

Return : -

setFooterProcName5

Type: Procedure

Description: Sets the page footer procedure name with 5 parameters. The program name passed as a parameter executes when the page footer is created. If SetFooterProcName is not executed before a page footer is created then the page footer will be empty.

Version: v3.0.0

Parameters :

- p_proc_name varchar2 : Page header procedure name
- p_height number : height of header section
- p_1 varchar2 default null : parameter of footer procedure
- p_2 varchar2 default null : parameter of footer procedure
- p_3 varchar2 default null : parameter of footer procedure
- p_4 varchar2 default null : parameter of footer procedure

PL/PDF

- p_5 varchar2 default null : parameter of footer procedure

Return : -

set3FooterProcName

Type: Procedure

Description : Sets the page footer procedure names. The program name passed as a parameter executes when the page footer is created.

Version: v3.0.1

Parameters :

- p_default_proc_name varchar2 default null : Specifies that this footer shall appear on every page in this section which is not overridden with a specific even or first page footer.
- p_first_proc_name varchar2 default null : Specifies that this footer shall appear on the first page in this document.
- p_even_proc_name varchar2 default null : Specifies that this footer shall appear on all even numbered pages in this document.
- p_height number : height of header section

Return : -

setBackgroundColor

Type: Procedure

Description : Sets the background color of the pages

Version: v3.0.0

Parameters :

- p_color plpdf_type.t_color : The color of the background

Return : -

SetWatermarkProcName

Type: Procedure

Description : Sets the name of the watermark creator procedure

Version: v3.0.0

Parameters :

- p_proc_name varchar2 : The name of the procedure

Return : -

SetStampProcName

Type: Procedure

Description : Sets the name of the stamp creator procedure

Version: v3.0.0

Parameters :

- p_proc_name varchar2 : The name of the procedure

Return : -

setNewPageProcName

Type: Procedure

Description : Sets the new page procedure name. The program name passed as a

PL/PDF

parameter executes when the page is started.

Version: v4.4.0

Parameters :

- p_proc_name varchar2 : New Page procedure name
- p_height number : height of this section

Return : -

setLeftMargin

Type: Procedure

Description: Sets the left margin size.

Version: v3.0.0

Parameters :

- p_margin number : Margin size

Return : -

setTopMargin

Type: Procedure

Description: Sets the top margin size.

Version: v3.0.0

Parameters :

- p_margin number : Margin size

Return : -

setRightMargin

Type: Procedure

Description: Sets the right margin size.

Version: v3.0.0

Parameters :

- p_margin number : Margin size

Return : -

setBottomMargin

Type: Procedure

Description: Sets the bottom margin size with autonewpage.

Version: v3.6.0

Parameters :

- p_margin number : Margin size

Return : -

setNOLastpageProcName

Type: Procedure

Description: Sets the not last page procedure name. The program name passed as a parameter executes when the not last page closed.

Version: v3.0.0

Parameters :

- p_proc_name varchar2 : Procedure name

PL/PDF

Return : -

SetPageNoStart

Type: Procedure

Description : Sets start of page numbering to the current page.

Version: v3.2.0

Parameters :

- p_start_num pls_integer default null : The start of the numbering, null means 1

Return : -

SetPageNoEnd

Type: Procedure

Description : Sets end of page numbering to the current page, see [SetPageNoStart](#) .

Version: v3.0.0

Parameters : -

Return : -

getPageNoAlter

Type: Function

Description : Gets page altering flag, see [SetPageNoStart](#) .

Version: v3.0.0

Parameters : -

Return : boolean : Altered or not

SetProtection

Type: Procedure

Description : Allows to protect the PDF document.

Version: v3.0.0

Parameters :

- p_print_perm Boolean default false : print the PDF
- p_modify_perm Boolean default false : modify the PDF
- p_annot_forms_perm Boolean default false : add annotations and forms
- p_user_pass varchar2 default null : user password
- p_owner_pass varchar2 default null : owner password

Return : -

setPDFAlB

Type: Procedure

Description : Set PDF/A-1B support.

Version: v3.0.0

Parameters : -

Return : -

setID

PL/PDF

Type: Procedure

Description: Sets the internal identifier of the PDF file. ID format is a 32 characters length hex string, possible generator is the "rawtohex(SYS_GUID())" expression.

Version: v3.0.0

Parameters :

- p_id varchar2 : ID value

Return : -

PL/PDF

Navigations and formatting commands

checkPageBreak

Type: Function

Description: If the height would cause an overflow, add a new page immediately, and return true.

Version: v3.0.0

Parameters:

- p_h number: height for check page overflow
- p_newpage boolean default true: do NewPage procedure

Return: boolean

- o true: overflow is reached
- o false: don't reach overflow

getCurrPageNum

Type: Function

Description: Returns the page number of the current page.

Version: v3.0.0

Parameters: -

Return: pls_integer: Page number of the current page

getNumOfPages

Type: Function

Description: Returns the number of pages, this procedure works in header and footer procedures only.

Version: v3.0.0

Parameters: -

Return: pls_integer: Number of pages

getLeftMargin

Type: Function

Description: Gets the page left margin size.

Version: v3.0.0

Parameters: -

Return: number: Size of left margin

getRightMargin

Type: Function

Description: Gets the page right margin size.

Version: v3.0.0

Parameters: -

Return: number: Size of right margin

getTopMargin

Type: Function
Description: Gets the page top margin size.
Version: v3.0.0
Parameters: -
Return: number: Size of top margin

getBottomMargin

Type: Function
Description: Gets the page bottom margin size.
Version: v3.0.0
Parameters: -
Return: number: Size of bottom margin

getHeaderHeight

Type: Function
Description: Gets the page header size.
Version: v3.0.0
Parameters: -
Return: number: Size of header

getFooterHeight

Type: Function
Description: Gets the page footer size.
Version: v3.0.0
Parameters: -
Return: number: Size of footer

getCurrentX

Type: Function
Description: Gets the X coordinate of the cursor.
Version: v3.0.0
Parameters: -
Return: number: X coordinate

getCurrentY

Type: Function
Description: Gets the Y coordinate of the cursor.
Version: v3.0.0
Parameters: -
Return: number: Y coordinate

getPageAvailableHeight

Type: Function
Description: Gets the available height (without margins) of actual page.
Version: v3.0.0

PL/PDF

Parameters : -

Return : number : Available height

getPageAvailableWidth

Type: Function

Description : Gets the available width (without margins) of actual page.

Version: v3.0.0

Parameters : -

Return : number : Available width

getPageHeight

Type: Function

Description : Gets the height of actual page.

Version: v3.0.0

Parameters : -

Return : number : The height of the page

getPageRightSpace

Type: Function

Description : Gets the available width (without margins) of actual page from current position.

Version: v3.0.0

Parameters : -

Return : number : Actual page available space

getPageLeftSpace

Type: Function

Description : Gets the available width (without margins) of actual page from current position.

Version: v3.0.0

Parameters : -

Return : number : Actual page available space

getPageSpace

Type: Function

Description : Gets the available width (without margins) of actual page from current position.

Version: v3.0.0

Parameters : -

Return : number : Actual page available space

getPageWidth

Type: Function

Description : Gets the width of actual page.

Version: v3.0.0

PL/PDF

Parameters : -

Return : number : Actual page width

getPageBottomSpace

Type: Function

Description : Gets the available height (without margins) of actual page from current position.

Version: v3.0.0

Parameters : -

Return : number : Actual page bottom space

getPrintFontKey

Type: Function

Description : Get the current font name and style. See [SetPrintFont](#) .

Version: v3.0.0

Parameters : -

Return : varchar2 : Font type

getPrintFontName

Type: Function

Description : Get the current font type. See [SetPrintFont](#) .

Version: v3.0.0

Parameters : -

Return : varchar2 : Font type

getPrintFontStyle

Type: Function

Description : Get the current font style. See [SetPrintFont](#)

Version: v3.0.0

Parameters : -

Return : varchar2 : Font style

getPrintFontSize

Type: Function

Description : Get the current font size. See [SetPrintFont](#)

Version: v3.0.0

Parameters : -

Return : varchar2 : Font size

getScaleFactor

Type: Function

Description : Get the current scale factor.

Version: v3.0.0

Parameters : -

Return : number : scale factor

getTextWidth

Type: Function

Description: Returns the width of the parameter text (uses current font).

Version: v3.0.0

Parameters:

- p_s varchar2 : Text

Return: number : The width of the text in the unit of measure specified in Init

getTextwidthFont

Type: Function

Description: Returns the width of the parameter text, font is a parameter too.

Version: v3.0.0

Parameters:

- p_family varchar2 default null : Font type, null means current font family
 - o Helvetica (Arial, Sans Serif)
 - o Courier
 - o Times (Serif)
 - o Symbol
 - o ZapfDingBats
 - o If TTF fonts were added using the AddTTF procedure then they may be used here as well.
- p_style varchar2 default null : Font style
 - o null: Regular
 - o B: Bold
 - o I: Italic
 - o U: Underline
 - o The styles may be combined (i.e. BI will be Bold and Italic)
- p_size number default null : Font size, null means current font size
- p_s varchar2 : Text

Return: number : The width of the text in the unit of measure specified in Init

removeMissingChars

Type: Function

Description: Remove unknown characters from text (uses current font).

Version: v3.0.0

Parameters:

- p_s varchar2 : Text

Return: varchar2 : The text without missing characters

insertMovePage

Type: Procedure

Description: Insert a new page and move it by changing order of pages.

Version: v3.0.0

Parameters:

- p_orig_pos number : origin page position
- p_new_pos number : new page position

Return: -

NewPage

Type: Procedure

Description: Creates a new page. If no orientation is given then the orientation specified in Init will be used. If a page was previously open, a page break is initiated and the cursor is placed at the top left corner of the new page.

Version: v3.0.0

Parameters:

- p_orientation varchar2 default NULL: Page orientation
 - o P: Portrait
 - o L: Landscape

Return: -

SetNoPrintFooter

Type: Procedure

Description: Disables the footer on the specified page.

Version: v3.0.0

Parameters:

- p_page pls_integer default null: Page number

Return: -

setNoPrintHeader

Type: Procedure

Description: Disables the header on the specified page.

Version: v4.9.6

Parameters:

- p_page pls_integer default null: Page number

Return: -

setCurrentX

Type: Procedure

Description: Places the cursor at the X coordinate.

Version: v3.0.0

Parameters:

- p_x number default 0: X coordinate

Return: -

setCurrentY

Type: Procedure

Description: Places the cursor at the Y coordinate and reset X.

Version: v3.0.0

Parameters:

- p_y number default 0: Y coordinate
- p_cr boolean default true: X position returns to beginning of line

Return: -

setCurrentXY

Type: Procedure

Description: Places the cursor at the X and Y coordinate.

Version: v3.0.0

Parameters:

- p_x number default 0 : X coordinate
- p_y number default 0 : Y coordinate

Return: -

NewLine

Type: Procedure

Description: Line break. Cursor is placed at the start of the next line.

Version: v3.0.0

Parameters:

- p_h number default 0 : Height of the line break.

Return: -

Content Related Commands

AttachFile

Type: Procedure

Description: Attachs a file to the PDF document.

Version: v3.0.0

Parameters:

- p_filename varchar2: name of file
- p_fileblob blob: file
- p_desc varchar2 default null: description of file

Return: -

crBookmark

Type: Procedure

Description: Create a bookmark in the PDF document. Bookmarks are displayed in the PDF viewer program (e.g. Acrobat Reader).

Version: v3.0.0

Parameters:

- p_txt varchar2: Text of the bookmark
- p_level number default 0: Bookmark level, 0 is the highest level
- p_y number default null: Y coordinate of the bookmark within the current page. Null denotes the cursor position.

Return: -

PrintoutText

Type: Procedure

Description: Prints a text starting from the specified position.

Version: v3.0.0

Parameters:

- p_x number: X coordinate for the start of the text
- p_y number default null: Y coordinate for the start of the text
- p_txt varchar2: Text

Return: -

Circle

Type: Procedure

Description: Draws a circle on the current page.

Version: v3.0.1

Parameters:

- p_x number: X coordinate of the center of the circle
- p_y number: Y coordinate of the center of the circle
- p_r number: the radius of the circle
- p_draw boolean default true: frame drawing
- p_fill boolean default false: filling
- p_draw_color plpdf_type.t_color default null: frame drawing color

PL/PDF

- p_fill_color plpdf_type.t_color default null : filling color
- p_linewidth number default null : The width of the frame line of the rectangle
- p_fill_pattern varchar2 default null : The filling pattern

Return : -

Ellipse

Type: Procedure

Description : Draws an ellipse on the current page.

Version: v3.0.1

Parameters :

- p_x number : X coordinate of the center of the ellipse
- p_y number : Y coordinate of the center of the ellipse
- p_rx number : horizontal radius of the ellipse
- p_ry number : vertical radius of the ellipse
- p_draw boolean default true : frame drawing
- p_fill boolean default false : filling
- p_draw_color plpdf_type.t_color default null : frame drawing color
- p_fill_color plpdf_type.t_color default null : filling color
- p_linewidth number default null : The width of the frame line of the rectangle
- p_fill_pattern varchar2 default null : The filling pattern

Return : -

Line

Type: Procedure

Description : Draws a line between the two positions on the page.

Version: v3.0.0

Parameters :

- p_x1 number : X coordinate for the start of the line
- p_y1 number : Y coordinate for the start of the line
- p_x2 number : X coordinate for the end of the line
- p_y2 number : Y coordinate for the end of the line
- p_color plpdf_type.t_color default null : color of the line
- p_width number default null : width of the line

Return : -

Polygon

Type: Procedure

Description : Draws a lines (polygon) between the points on the page.

Version: v3.0.1

Parameters :

- p_points plpdf_type.t_points : set of ordered points
- p_draw boolean default true : frame drawing
- p_fill boolean default false : filling
- p_draw_color plpdf_type.t_color default null : frame drawing color
- p_fill_color plpdf_type.t_color default null : filling color
- p_linewidth number default null : The width of the frame line of the

PL/PDF

rectangle

- p_fill_pattern varchar2 default null : The filling pattern

Return : -

Path

Type: Procedure

Description : Draws a lines between the points on the page.

Version: v3.6.0

Parameters :

- p_operators plpdf_type.t_path_operators : set of ordered operators defined in the PDF Reference. Supported Operators: m,l,c,v,y,h,re
- p_draw boolean default true : frame drawing
- p_fill boolean default false : filling
- p_draw_color plpdf_type.t_color default null : frame drawing color
- p_fill_color plpdf_type.t_color default null : filling color
- p_linewidth number default null : The width of the frame line of the rectangle
- p_fill_pattern varchar2 default null : The filling pattern

Return : -

Rect

Type: Procedure

Description : Draws a rectangle on the page.

Version: v3.0.0

Parameters :

- p_x number : X coordinate for the top left corner of the rectangle
- p_y number : Y coordinate for the top left corner of the rectangle
- p_w number : The width of the rectangle
- p_h number : The height of the rectangle
- p_draw boolean default true : frame drawing
- p_fill boolean default false : filling
- p_draw_color plpdf_type.t_color default null : frame drawing color
- p_fill_color plpdf_type.t_color default null : filling color
- p_linewidth number default null : The width of the frame line of the rectangle
- p_fill_pattern varchar2 default null : The filling pattern

Return : -

RoundedRect

Type: Procedure

Description : Draws a rectangle on the page.

Version: v3.0.1

Parameters :

- p_x number : X coordinate for the top left corner of the rectangle
- p_y number : Y coordinate for the top left corner of the rectangle
- p_w number : The width of the rectangle
- p_h number : The height of the rectangle
- p_r number : The radius of the corners

PL/PDF

- p_draw boolean default true : frame drawing
- p_fill boolean default false : filling
- p_draw_color plpdf_type.t_color default null : frame drawing color
- p_fill_color plpdf_type.t_color default null : filling color
- p_linewidth number default null : The width of the frame line of the rectangle
- p_fill_pattern varchar2 default null : The filling pattern

Return : -

Sector

Type: Procedure

Description : Draws a sector on the current page.

Version: v3.0.1

Parameters :

- p_xc number : X coordinate of the center of the sector
- p_yc number : Y coordinate of the center of the sector
- p_r number : Radius of the sector
- p_a number : Starting point of the sector
- p_b number : End point of the sector
- p_draw boolean default true : frame drawing
- p_fill boolean default false : filling
- p_draw_color plpdf_type.t_color default null : frame drawing color
- p_fill_color plpdf_type.t_color default null : filling color
- p_linewidth number default null : The width of the frame line of the rectangle
- p_fill_pattern varchar2 default null : The filling pattern
- p_cw boolean default true : Draw direction
 - o true: Clockwise
 - o false: Anti-clockwise
- p_o number default 90 : origin of angles

Return : -

EndOpacity

Type: Procedure

Description : End a transparency. See [StartOpacity](#)

Version: v3.0.0

Parameters : -

Return : -

EndOptCont

Type: Procedure

Description : End an optional content. See [link StartOptCont](#)

Version: v3.0.0

Parameters : -

Return : -

putImage

PL/PDF

Type: Procedure

Description: Inserts an image (JPG, BMP, PNG, etc.) from a BLOB variable into the current page.

Version: v3.0.1

Parameters:

- p_name varchar2: Image name or ID, if the name is equal with an earlier used image name then procedure reuses the original blob
- p_data blob: Variable containing the image as binary data
- p_x number: X coordinate of the image
- p_y number: Y coordinate of the image
- p_w number default null: Image width, if null then the image is displayed in its actual width
- p_h number default null: Image height, if null then the image is displayed in its actual height
- p_link varchar2 default NULL: URL or internal link ID

Return: -

putImage

Type: Procedure

Description: Inserts an image (JPG, BMP, PNG, etc.) from a BLOB variable into the current page.

Version: v3.0.1

Parameters:

- p_name varchar2: The name is an earlier used image name and procedure reuse this image blob.
- p_x number: X coordinate of the image
- p_y number: Y coordinate of the image
- p_w number default null: Image width, if null then the image is displayed in its actual width
- p_h number default null: Image height, if null then the image is displayed in its actual height
- p_link varchar2 default NULL: URL or internal link ID

Return: -

putImage

Type: Procedure

Description: Inserts an image (JPG, BMP, PNG, etc.) from a BLOB variable into the current page.

Version: v3.0.1

Parameters:

- p_data blob: Variable containing the image as binary data
- p_x number: X coordinate of the image
- p_y number: Y coordinate of the image
- p_w number default null: Image width, if null then the image is displayed in its actual width
- p_h number default null: Image height, if null then the image is displayed in its actual height
- p_link varchar2 default NULL: URL or internal link ID

Return: -

putInternalLink

Type: Procedure

Description: Puts a link area on the page that point to an internal link.

Version: v3.0.0

Parameters:

- p_x number: X coordinate of the top left corner of the area
- p_y number: Y coordinate of the top left corner of the area
- p_w number: Link area width
- p_h number: Link area height
- p_link pls_integer: Internal link ID returned by crInternalLinkDest

Return: -

putExternalLink

Type: Procedure

Description: Puts a link area on the page that point to an external link.

Version: v3.0.0

Parameters:

- p_x number: X coordinate of the top left corner of the area
- p_y number: Y coordinate of the top left corner of the area
- p_w number: Link area width
- p_h number: Link area height
- p_link varchar2: External link

Return: -

putLink

Type: Procedure

Description: Puts a link area on the page that point to an external link. If p_link is a number then internal if string then external link.

Version: v3.0.0

Parameters:

- p_x number: X coordinate of the top left corner of the area
- p_y number: Y coordinate of the top left corner of the area
- p_w number: Link area width
- p_h number: Link area height
- p_link varchar2: Identification of the link

Return: -

setStrokingColor

Type: Procedure

Description: Sets the color for stroking operation. Colors must be specified according to the RGB pallet.

Version: v3.0.0

Parameters:

- p_color plpdf_type.t_color: color

Return: -

setNonStrokingColor

PL/PDF

Type: Procedure

Description: Sets the color for non stroking operation. Colors must be specified according to the RGB pallet.

Version: v3.0.0

Parameters:

- p_color plpdf_type.t_color: color

Return: -

addJavaScript

Type: Procedure

Description: Add JavaScript inside the PDF. See Acrobat JavaScript Reference.

Version: v3.0.0

Parameters:

- p_name varchar2: Name of the script
- p_text varchar2: The script

Return: -

LineWidth

Type: Procedure

Description: Sets the thickness of lines drawn after this statement.

Version: v3.0.0

Parameters:

- p_width number: Line thickness

Return: -

crInternalLink

Type: Function

Description: Creates an internal link, and returns its ID. An internal link can be used to take the cursor to another place within the document by clicking over it.

Version: v3.0.0

Parameters: -

Return: number: The ID of the internal link

setLinkDest

Type: Procedure

Description: Sets the destination page and position for the internal link.

Version: v3.0.0

Parameters:

- p_link number: Internal link ID returned by CrInternalLink
- p_y number default 0: Y position on the page, if null then the current Y coordinate, if 0 then the top of the page
- p_page number default null: Page number, if null then the current page

Return: -

crInternalLinkDest

PL/PDF

Type: Function

Description: Create the destination page and position for the internal link.

Version: v3.0.0

Parameters:

- p_page pls_integer default null: Page number, if null then the current page
- p_y number default null: Y position on the page, if null then the current Y coordinate, if 0 then the top of the page

Return: Internal link ID

setPrintFont

Type: Procedure

Description: Sets the font and its properties.

Version: v3.0.0

Parameters:

- p_family varchar2 default NULL: Font type
 - o Helvetica (Arial, Sans Serif)
 - o Courier
 - o Times (Serif)
 - o Symbol
 - o ZapfDingBats
 - o If TTF fonts were added using the AddTTF procedure then they may be used here as well.
- p_style varchar2 default NULL: Font style
 - o null: Regular
 - o B: Bold
 - o I: Italic
 - o U: Underline
 - o The styles may be combined (i.e. BI will be Bold and Italic)
- p_size number default null: Font size, null means the current size. If no size has been specified then value is 12.

Return: -

setPrintFontSize

Type: Procedure

Description: Sets the font size. All other font properties remain unchanged.

Version: v3.0.0

Parameters:

- p_size number: Font size

Return: -

setRotate

Type: Procedure

Description: Sets the degree of rotation. Text and images can both be rotated.

Version: v3.0.0

Parameters:

- p_angle number: Angle/degree of rotation
- p_x number default null: X coordinate of the rotation point, if null then the X coordinate of the cursor

PL/PDF

- p_y number default null : Y coordinate of the rotation point, if null then the Y coordinate of the cursor

Return : -

startClipping

Type: Procedure

Description : Starts a clipping frame. The clipping limits the region that can be paint. The clipping affects forobjects wich located between StartClipping and EndClipping.

Version: v3.0.0

Parameters :

- p_x number : X coordinate for the start of the clipping frame
- p_y number : Y coordinate for the start of the clipping frame
- p_w number : height of clipping frame
- p_h number : width of clipping frame

Return : -

EndClipping

Type: Procedure

Description : End a clipping frame. See [StartClipping](#)

Version: v3.0.0

Parameters : -

Return : -

isInClipping

Type: Function

Description : Get the state of clipping.

Version: v3.0.0

Parameters : -

Return : boolean: in clipping or not

startOpacity

Type: Procedure

Description : Starts a transparency. The transparency affects forobjects wich located between StartOpacity and EndOpacity.

Version: v3.0.0

Parameters :

- p_val number : can be a value from 0.0 - 1.0. A lower value makes the element more transparent.

Return : -

startOptCont

Type: Procedure

Description : Start an optional content.

Version: v3.0.0

Parameters :

PL/PDF

- p_name varchar2 : name of optional content
- p_state boolean default true : default state is visible or invisible
- p_ui_order boolean default true : insert into the state array
- p_print boolean default true : printed out

Return : -

Template Related Commands

InsTemplate

Type: Function

Description: Insert a template into the pdf.

Version: v3.0.0

Parameters:

- p_tpl plpdf_type.tr_tpl_data: template data

Return: pls_integer: template ID

setPageTemplate

Type: Procedure

Description: Use a template.

Version: v4.9.2

Parameters:

- p_page pls_integer default null: page, Null means current page
- p_tplidx pls_integer: template ID
- p_fittopage boolean default true: fit template to page size
- p_rotate90 boolean default false: rotate template right with 90

Return: -

setPageDefaultTemplate

Type: Procedure

Description: Set template for all new page. Remove template when p_tplidx is null.

Version: v3.0.0

Parameters:

- p_tplidx pls_integer: template ID
- p_fittopage boolean default true: fit template to page size

Return: -

UseTemplate

Type: Procedure

Description: Use a template in the page content.

Version: v4.9.3

Parameters:

- p_tplidx pls_integer: template ID
- p_fittopage boolean default true: fit template to page size

Return: -

Digital Signature Related Commands

setDigSig

Type: Procedure

Description: Set digital signature appearances.

Version: v3.0.0

Parameters:

- p_Name varchar2 default null: The name of the person or authority signing the document.
- p_Location varchar2 default null: The CPU host name or physical location of the signing.
- p_Reason varchar2 default null: The reason for the signing, such as (I agree?).
- p_ContactInfo varchar2 default null: Information provided by the signer to allow a recipient to contact the signer to verify the signature; for example, a phone number.
- p_access_perms: The access permissions granted for this document. Defined values are:
 - o 1: No changes to the document are permitted; any change to the document invalidates the signature.
 - o 2: Permitted changes are filling in forms, instantiating page templates, and signing; other changes invalidate the signature.
 - o 3: Permitted changes are those allowed by 2, as well as annotation creation, deletion, and modification; other changes invalidate the signature.

Return: -

setNeedAppearances

Type: Procedure

Description: Set Need Appearances property for Acroform fields.

Version: v3.0.0

Parameters: -

Return: -

getCalcCurrPageNum

Type: Function

Description: Gets the calculated number of the page.

Version: v3.0.0

Parameters:

- p_page pls_integer: The page number

Return: pls_integer: page number

getCalcCurrPageNum

Type: Function

Description: Gets the calculated amount number of the pages.

PL/PDF

Version: v3.0.0

Parameters :

- p_page pls_integer : The page number

Return : pls_integer : number of pages

PL/PDF

PL/PDF v2 Compatible procedures and functions

LineBreak

Type: Procedure

Description: Line break. Cursor is placed at the start of the next line.

Version: v3.0.0

Parameters:

- p_h number default NULL: Height of the line break. If not set, then the last printed cells height is the height by default.

Return: -

setLineWidth

Type: Procedure

Description: Sets the thickness of lines drawn after this statement.

Version: v3.0.0

Parameters:

- p_width number: Line thickness

Return: -

getLineWidth

Type: Function

Description: Gets the current line size.

Version: v3.0.0

Parameters: -

Return: number: Line size

DrawLine

Type: Procedure

Description: Draws a line between the two positions on the page.

Version: v3.0.0

Parameters:

- p_x1 number: X coordinate for the start of the line
- p_y1 number: Y coordinate for the start of the line
- p_x2 number: X coordinate for the end of the line
- p_y2 number: Y coordinate for the end of the line

Return: -

DrawRect

Type: Procedure

Description: Draws a rectangle on the page.

Version: v3.0.0

Parameters:

- p_x number: X coordinate for the top left corner of the rectangle
- p_y number: Y coordinate for the top left corner of the rectangle

- p_w number : The width of the rectangle
- p_h number : The height of the rectangle
- p_style varchar2 default NULL : Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF or FD: Fill and border line

Return : -

drawRoundedRect

Type: Procedure

Description : Draws a rectangle on the page.

Version: v3.0.0

Parameters :

- p_x number : X coordinate for the top left corner of the rectangle
- p_y number : Y coordinate for the top left corner of the rectangle
- p_w number : The width of the rectangle
- p_h number : The height of the rectangle
- p_r number : The radius of the corners
- p_style varchar2 default NULL : Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF or FD: Fill and border line

Return : -

DrawEllipse

Type: Procedure

Description : Draws an ellipse on the current page.

Version: v3.0.0

Parameters :

- p_x number : X coordinate of the center of the ellipse
- p_y number : Y coordinate of the center of the ellipse
- p_rx number : horizontal radius of the ellipse
- p_ry number : vertical radius of the ellipse
- p_style varchar2 default 'D' : Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF or FD: Fill and border line

Return : -

DrawCircle

Type: Procedure

Description : Draws a circle on the current page.

Version: v3.0.0

Parameters :

- p_x number : X coordinate of the center of the circle
- p_y number : Y coordinate of the center of the circle
- p_r number : the radius of the circle
- p_style varchar2 default NULL : Style

- o D: No fill, border line
- o F: Fill, no border line
- o DF or FD: Fill and border line

Return : -

drawSector

Type: Procedure

Description : Draws a sector on the current page.

Version: v3.0.0

Parameters :

- p_xc number : X coordinate of the center of the sector
- p_yc number : Y coordinate of the center of the sector
- p_r number : Radius of the sector
- p_a number : Starting point of the sector
- p_b number : End point of the sector
- p_style varchar2 default 'FD' : Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF vagy FD: Fill and border line
- p_cw boolean default true : Draw direction
 - o true: Clockwise
 - o false: Anti-clockwise
- p_o number default 90 : origin of angles

Return : -

DrawPolygon

Type: Procedure

Description : Draws a lines (polygon) between the points on the page.

Version: v3.0.0

Parameters :

- p_points plpdf_type.t_points : set of ordered points
- p_style varchar2 default 'D' : Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF or FD: Fill and border line

Return : -

PrintText

Type: Procedure

Description : Prints a text starting from the specified position.

Version: v3.0.0

Parameters :

- p_x number : X coordinate for the start of the text
- p_y number : Y coordinate for the start of the text
- p_txt varchar2 : Text

Return : -

setCellMargin

Type: Procedure
Description: Sets the cell margin size.
Version: v3.0.0
Parameters:
- p_margin number : Margin size
Return: -

getCellMargin

Type: Function
Description: Gets the cell margin size.
Version: v3.0.0
Parameters: -
Return: number : Margin size

setCellBottomMargin

Type: Procedure
Description: Sets the cell bottom margin size.
Version: v3.0.0
Parameters:
- p_margin number : Margin size
Return: -

setCellLeftMargin

Type: Procedure
Description: Sets the cell left margin size.
Version: v3.0.0
Parameters:
- p_margin number : Margin size
Return: -

setCellRightMargin

Type: Procedure
Description: Sets the cell right margin size.
Version: v3.0.0
Parameters:
- p_margin number : Margin size
Return: -

setCellTopMargin

Type: Procedure
Description: Sets the cell top margin size.
Version: v3.0.0
Parameters:
- p_margin number : Margin size
Return: -

getCellBottomMargin

Type: Function
Description: Gets the cell bottom margin size.
Version: v3.0.0
Parameters: -
Return: number: Size of bottom margin

getCellLeftMargin

Type: Function
Description: Gets the cell left margin size.
Version: v3.0.0
Parameters: -
Return: number: Size of left margin

getCellRightMargin

Type: Function
Description: Gets the cell right margin size.
Version: v3.0.0
Parameters: -
Return: number: Size of right margin

getCellTopMargin

Type: Function
Description: Gets the cell top margin size.
Version: v3.0.0
Parameters: -
Return: number: Size of top margin

getTextHeight

Type: Function
Description: Gets the height of the actual font.
Version: v3.4.0
Parameters: -
Return: number: The size of the actual font

getCellMinHeight

Type: Function
Description: Gets the minimum cell height (uses current font).
Version: v3.0.0
Parameters: -
Return: number

getCellMinHeightFont

Type: Function

PL/PDF

Description: Gets the minimum cell height, font is parameter.

Version: v3.0.0

Parameters:

- p_family varchar2 default null: Font type, null means current font family
 - o Helvetica (Arial, Sans Serif)
 - o Courier
 - o Times (Serif)
 - o Symbol
 - o ZapfDingBats
 - o If TTF fonts were added using the AddTTF procedure then they may be used here as well.
- p_style varchar2 default null: Font style
 - o null: Regular
 - o B: Bold
 - o I: Italic
 - o U: Underline
 - o The styles may be combined (i.e. BI will be Bold and Italic)
- p_size number default null: Font size, null means current font size

Return: number

getCellMinWidth

Type: Function

Description: Gets the minimum cell width (uses current font).

Version: v3.0.0

Parameters:

- p_txt varchar2: Text for calculating width

Return: number

getCellMinWidthFont

Type: Function

Description: Gets the minimum cell width, font is parameter.

Version: v3.0.0

Parameters:

- p_family varchar2 default null: Font type, null means current font family
 - o Helvetica (Arial, Sans Serif)
 - o Courier
 - o Times (Serif)
 - o Symbol
 - o ZapfDingBats
 - o If TTF fonts were added using the AddTTF procedure then they may be used here as well.
- p_style varchar2 default null: Font style
 - o null: Regular
 - o B: Bold
 - o I: Italic
 - o U: Underline
 - o The styles may be combined (i.e. BI will be Bold and Italic)
- p_size number default null: Font size, null means current font size
- p_txt varchar2: Text for calculating width

Return : number

PrintCell

Type: Procedure

Description : Draws a rectangle cell with text inside. The rectangle may have a border and fill color specified.

Version: v4.8.0

Parameters :

- p_w number default 0 : Rectangle width
 - o 0: the rectangle will extend till the right margin
 - o null: uses minimum cell width
- p_h number default 0 : Rectangle height
 - o null: uses minimum cell height
 - o -1: uses minimum cell height
 - o 0: uses last cell height
- p_txt varchar2 default NULL : Text
- p_border varchar2 default '0' : Rectangle border
 - o 0: no border
 - o 1: outline border
 - o L: left side border
 - o T: top side border
 - o R: right side border
 - o B: bottom side border
 - o or a combination of L, T, R and B
- p_ln number default plpdf_const.beside : Cursor position after the cell is printed
 - o 0: Beside the cell
 - o 1: New line
 - o 2: Under the cell
- p_align varchar2 default NULL : Text alignment
 - o L: left
 - o R: right
 - o C:
 - o J: Force Justification
- p_fill boolean default false : Fill with current fill color
 - o false: no fill
 - o true: fill with current fill color
- p_link varchar2 default null : Link related to the text, can be a URL or an internal link ID
- p_clipping boolean default true : Clipping the cell
 - o false: no clipping
 - o true: clipping
- p_vert_align varchar2 default null : Text vertical alignment in cell
 - o null: normal
 - o T: top
 - o B: bottom

Return : -

PrintMultiLineCell

Type: Procedure

Description: Draws a multi line cell.

Version: v3.0.0

Parameters:

- p_w number default 0: Rectangle width, if 0 then the rectangle will extend till the right margin
- p_h number default 0: Rectangle height
 - o null: uses minimum cell height
 - o -1: uses minimum cell height
 - o 0: uses last cell height
- p_txt varchar2 default null: Text
- p_border varchar2 default '0': Rectangle border
 - o 0: no border
 - o 1: outline border
 - o L: left side border
 - o T: top side border
 - o R: right side border
 - o B: bottom side border
 - o Or a combination of L, T, R and B
- p_align varchar2 default 'J': Text alignment
 - o L: left
 - o R: right
 - o C: center
 - o J: force justification
- p_fill boolean default false: Fill with current fill color
 - o false: no fill
 - o true: fill with current fill color
- p_maxline number default 0: Maximum number of lines displayed. If 0 then all lines will be displayed.
- p_link varchar2 default NULL: Link related to the text, can be a URL or an internal link ID
- p_clipping boolean default true: Clipping cell
 - o false: no clipping
 - o true: clipping
- p_indent number default 0: First line Indent
- p_ln number default plpdf_const.newline: Cursor position after the cell is printed
 - o 0: Beside the cell
 - o 1: New line
 - o 2: Under the cell

Return: -

PrintFlowingText

Type: Procedure

Description: Prints text continuously. Text is wrapped according to the right margin.

Version: v3.0.0

Parameters:

- p_h number default 0: Rectangle height
 - o null: uses minimum cell height

- o -1: uses minimum cell height
- o 0: uses last cell height
- p_txt varchar2 default null : Text
- p_link varchar2 default null : URL or internal link ID
- p_align varchar2 default NULL : Text alignment
 - o L: left
 - o R: right
 - o C:
 - o J: Force Justification
- p_clipping boolean default true : Clipping text
 - o false: no clipping
 - o false: clipping
- p_lastline_j varchar2 default 'L' : justified text last line alignment
 - o L: left
 - o R: right
 - o C: center
 - o J: Force Justification

Return : -

PrintFlowingTextLimit

Type: Procedure

Description: Prints text continuously. Text is wrapped according to the p_min_x and p_max_x.

Version: v3.0.0

Parameters :

- p_h number default 0 : Rectangle height
 - o null: uses minimum cell height
 - o -1: uses minimum cell height
 - o 0: uses last cell height
- p_txt varchar2 default null : Text
- p_link varchar2 default null : URL or internal link ID
- p_min_x number default 0 : min X position, 0 means the limit is the left margin
- p_max_x number default 0 : max X position, 0 means the limit is the right margin
- p_align varchar2 default NULL : Text alignment
 - o L: left
 - o R: right
 - o C:
 - o J: Force Justification
- p_clipping boolean default true : Clipping text
 - o false: no clipping
 - o true: clipping
- p_lastline_j varchar2 default 'L' : justified text last line alignment
 - o L: left
 - o R: right
 - o C:
 - o J: Force Justification

Return : -

PrintImageCell

Type: Procedure

Description: Print an image with frame.

Version: v3.0.0

Parameters:

- p_w number: Width of frame
- p_h number: Height of frame
- p_name varchar2: name of image
- p_data blob: image
- p_margin number default 0: margin size of frame
- p_border varchar2 default '0': Rectangle border
 - o 0: no border
 - o 1: outline border
 - o L: left side border
 - o T: top side border
 - o R: right side border
 - o B: bottom side border
 - o Or a combination of L, T, R and B
- p_ln number default plpdf_const.beside: Cursor position after the cell is printed
 - o 0: Beside the cell
 - o 1: New line
 - o 2: Under the cell
- p_fill boolean default false: Fill with current fill color
 - o false: no fill
 - o true: fill with current fill color
- p_link varchar2 default NULL: URL or internal link ID
- p_type varchar2 default null: when use Oracle InterMedia then ignore this param, when does not use Oracle InterMedia then JPG or PNG, null means JPG

Return: -

setColor4Drawing

Type: Procedure

Description: Sets the line color for objects (line, rectangle, circle etc.) inserted after this statement. Colors must be specified according to the RGB pallet.

Version: v3.0.0

Parameters:

- p_r number: Red component code, can be between 0 and 255
- p_g number: Green component code, can be between 0 and 255
- p_b number: Blue component code, can be between 0 and 255

Return: -

setColor4Drawing

Type: Procedure

Description: Sets the line color for objects (line, rectangle, circle etc.) inserted after this statement. Colors must be specified according to the RGB pallet.

PL/PDF

Version: v3.0.0

Parameters :

- p_color plpdf_type.t_color : color

Return : -

setColor4Filling

Type: Procedure

Description : Sets the fill color for objects inserted after this statement. Colors must be specified according to the RGB pallet.

Version: v3.0.0

Parameters :

- p_r number : Red component code, can be between 0 and 255

- p_g number : Green component code, can be between 0 and 255

- p_b number : Blue component code, can be between 0 and 255

Return : -

setColor4Filling

Type: Procedure

Description : Sets the fill color for objects inserted after this statement. Colors must be specified according to the RGB pallet.

Version: v3.0.0

Parameters :

- p_color plpdf_type.t_color : color

Return : -

setColor4Text

Type: Procedure

Description : Sets the text color for objects inserted after this statement. Colors must be specified according to the RGB pallet.

Version: v3.0.0

Parameters :

- p_r number : Red component code, can be between 0 and 255

- p_g number : Green component code, can be between 0 and 255

- p_b number : Blue component code, can be between 0 and 255

Return : -

setColor4Text

Type: Procedure

Description : Sets the text color for objects inserted after this statement. Colors must be specified according to the RGB pallet.

Version: v3.0.0

Parameters :

- p_color plpdf_type.t_color : color

Return : -

getColor4Drawing

PL/PDF

Type: Function

Description: Gets the line color for objects.

Version: v3.0.0

Parameters: -

Return: plpdf_type.t_color: Drawing color

getColor4Filling

Type: Function

Description: Gets the filling color for objects.

Version: v3.0.0

Parameters: -

Return: plpdf_type.t_color: Filling color

getColor4Text

Type: Function

Description: Gets the color of text.

Version: v3.0.0

Parameters: -

Return: plpdf_type.t_color: Color of text